



VPHybridCAD V14 / VPmap Series V7 – what's new?

General

AutoCAD 2017 support

Improved: Print (Stand-Alone)

Menu: File ▶ Print...

· New: Load and save of print settings

Improved: Element selection (Stand-Alone)

• New: Polygon selection

New: Coordinate system - datum transform on change of projection

· multiple transform operations to change from one projection to an other

New: Revision Compare(Stand-Alone)



- compare to file (Raster and/or Vector). The differences will be highlighted
- adjust the file to compare to fit the original (rotate, scale, move)

New: Circle by Tangents (Stand-Alone)



• construct circle by selecting 2 circles/arcs and a radius or by 3 circles/arcs.

New: Chamfer and Filet (Stand-Alone)



- chamfer or fillet of edges and nodes (Vector and Raster)
- with Preview

Improved: Script Generator

Menu: File ► Create Script ...

· New: command filter for easy search

Improved: Raster Text



• New: copy text to the clipboard for use in other applications

Improved: Combine to Text



New: copy text to the clipboard for use in other applications





New: Layer select (Stand-Alone)




· set the Layer of a selected entity to current

New: Color select (Stand-Alone)



· set the Color of a selected entity to current

New: Linetype select (Stand-Alone)



set the Linetype of a selected entity to current

New: Textstyle select (Stand-Alone)



· set the Textstyle of a selected text to current

Improved: Direct Raster Selection

Toolbar Direct raster Selection methods

• switch between permanent and temporary selection method (click with [Ctrl]+[Shift] onto one of the lcon)

Additional Improvements

• Improved Zoom and Preview for (Color-)Palette transformation





VPindex V7 – what's new?

General

• all improved and new functions of VPHybridCAD V14, as far as available in VPindex

Improved: OCR

• New: barcode-recognition (1-D and 2D- QR-Code)

Improved: File management

• New: "remove file from input folder" handling in case of an error

Improved: Template Creation

• New: test of the selected OCR-settings for each cell

Improved: Logging

• New: process logging for one job only

Improved: Date Entry

• New: field value (= recognized text) can be displayed directly in the drawing for more easy compare